

RIEGL-VZi ROS 2 Driver API

1. Coordinate Systems

RIEGL uses hierarchically structured coordinate systems:

SOCS (Scanner's Own Coordinate System): Angle data and range data are the base for calculation of the data in the Scanner's Own Coordinate System (SOCS).




Figure 1: SOCS

PRCS (Project Coordinate System): A number of scan positions and the data acquired therein make up a scan project. The center of the project's coordinate system (PRCS) usually coincides horizontally with the center of the first scan position. The axes of PRCS are strictly pointing to east (x-axis, red), north (y-axis, green) and up (z-axis, blue), respectively.





Figure 2: PRCS

VOCS (Voxel Coordinate System): This is an intermediate coordinate system.

Origin and orientation are identical to PRCS at the first scan position. Each scan will be registered in the VOCS coordinate system. * Every scan position is described by SOPV (Scan Orientation and Position in VOCS). * The position of the VOCS is described by VOP (VOCS Orientation and Position in PRCS). * With every scan the VOP, especially the orientation, will be readjusted. * The SOP (Scan Position and Orientation in PRCS) has to be recalculated after each newly registered scan from SOPV and updated VOP.



2. RIEGL Interfaces

2.1 Messages

riegl_vzi_interfaces/Status:

```

uint8 errors
uint8 warnings
uint8 scan_progress
uint8 memory_usage
tbd...

```

2.2 Services

riegl_vzi_interfaces/GetPointcloud:

```

uint32 n
---
PointCloud2 pointcloud

```

See PointCloud2 definition: `sensor_msgs/PointCloud2`

riegl_vzi_interfaces/GetPose:

```

int32 first
int32 last
---
PoseStamped vop

```

PoseStamped sopv[]

PoseStamped sop[]

A negative value of n/first/last points to the last scan position. 0 ist the first scan position.

See PoseStamped definition: sensor_msgs/PoseStamped[]

3. Nodes

3.1 riegl_vz

3.1.1 Parameters

~hostname (string, default: “”) :

The scanners hostname or IP address.

~ssh_user (string, default: “user”) :

The linux user name for SSH login on the scanner.

~ssh_password (string, default: “user”) :

The linux user password for SSH login on the scanner.

~scan_pattern (string, default: “Overview”) :

The scan pattern for laser scanning, specifying the field of view (FOV) and the delta angles between laser shots on line and frame angle.

~meas_prog (integer, default: 0) :

The laser scanners measurement program, defining the laser pulse repetition rate (PRR).

~stor_media (integer, default: 2) :

Automatically increment scan position before every data acquisition start.

~coarse_registration (bool, default: False) :

Enable coarse registration. If coarse registration fails, the standard registration method will be applied.

~pointcloud_msm (integer[], default: {1,1}) :

The point cloud MSM (monitor step multiplier) configuration, used for scan data reduction, default disabled ([0]: lines, [1]: shots).

3.1.2 Published Topics

pointcloud (sensor_msgs/PointCloud2) :

Point cloud with scan data from the laser scanner in SOCS.

status (riegl_vzi_interfaces/Status) :

Riegl VZ scanner status, provided once per second.

3.1.3 Services

create_project (std_srvs/Trigger) :

Create a new or load an existing project on the scanner with name composed from current local time (date and time).

Returns:

success = True -> message: Project Name

success = False -> message: Error Message

scan (std_srvs/Trigger) :

Acquire laser scan data. Start scan and wait until finished. When the scan has finished data is published on 'pointcloud' topic.

Returns:

success = True -> message: Measurement Identifier

success = False -> message: Error Message

get_pointcloud (riegl_vzi_interfaces/GetPointcloud) :

Get point cloud data of a previously acquired scan position.

scan_register (std_srvs/Trigger) :

Start laser scan registration in actual project and wait until finished. Provide estimated position on 'pose' topic.

Returns:

success = True -> message: SUCCESS

success = False -> message: Error Message

get_pose (riegl_vzi_interfaces/GetPose) :

Request VOP, SOPV and SOP for scan position(s).

shutdown (std_srvs/Trigger) :

Shutdown the laser scanner.

Returns:

success = True -> message: SUCCESS

success = False -> message: Error Message